



DVCAM/MiniDV Digital Transfer Using QuickTime



Step 1: Setup

- Make sure the DVCAM deck is powered on. The power light should be green.
- Gently insert your tape into the DVCAM deck, window up, ribbon edge first. The cassette will automatically load once placed in the proper position.
- Rewind your tape, if applicable.



Step 2: Open QuickTime Player

- Close all open programs, if any, on the Mac.
- Click on the **QuickTime Player** icon in the dock at the bottom of the screen.



Step 3: Getting started

- **QuickTime Player** will open a window allowing you to open an existing movie or project. Ignore this window.
 - Click on the **File** dropdown menu and select **New Movie Recording**.
 - A new window will open. This is what you will use to capture your DVCAM recording.

Step 4: Connect video and audio

- Click on the small, inverted caret next to the red **RECORD** button on the toolbar window that appears when you move the mouse.
 - Make sure that **DSR-11** is selected for both the “Camera” and “Audio” settings.
 - Select “High” for the quality setting, which will export into an MOV file using H.264 (video) and AAC (audio) codecs.
 - “Maximum” quality will export into an *extremely* large MOV file, using Apple ProRes 4444 (video) and 24-bit uncompressed LPCM (audio) codecs. This option should rarely be used..



Step 5: Capture your video

- Click on the red **RECORD** button in **QuickTime Player**.
- Press **PLAY** on the DVCAM deck.
- You should see and hear your movie playing in the window.
- When you want to stop recording, click on the **STOP** button in the software, then press **STOP** on the DVCAM deck.

Step 6: Export your video

- To export what you have just captured, go to **File** and select **Save** on the dropdown menu.
- Give your movie a title, then save it to the desktop.
 - It is **not recommended** to export directly to your external storage device.
- An MOV file should appear on the desktop with the title you gave it.

Step 7: Copy your video to your storage device

- Plug in your storage device to the USB hub.
- Drag the MOV file from the desktop to the disk image of your storage device.
- Once it has finished copying, safely eject your device from the computer by dragging its disk image to the eject icon (trash can) on the bottom of the desktop. Or you can click on the drive and select **File → Eject**.
- Rewind your tape then eject it from the DVCAM deck using the eject button located on the right side of the cassette compartment



Don't forget your tape and storage device!

